

Panopto Settings for BKENG Grand Hall

Best Camera: USB Capture HDMI

Best Microphone/Audio: HDMI (2- USB Capture HDMI)

Document Camera: Set Secondary Source to ET05R

Laptop Capture: (Not recommended—high difficulty) Start recording from computer in classroom, Set room to Laptop, connect via ShareLink, Set Secondary Source to USB Capture HDMI



A screenshot of the Panopto web application interface. The top navigation bar includes "Create New Recording", "Manage Recordings", and "Settings". The user is logged in as "unified\PRICESW". The "Session Settings" section shows a "Webcast" checkbox checked and circled in red. Below this, the "Folder" is "unified\pricesw" and the "Name" is "Thursday, August 13, 2020 at 9:13:31 AM". The "Primary Sources" section shows a video preview of a classroom. Below the preview, the "Video" dropdown is set to "USB Capture HDMI", "Audio" to "HDMI (2- USB Capture HD)", and "Quality" to "Standard". The "Capture Computer Audio" checkbox is unchecked. In the "Secondary Sources" section, "Capture PowerPoint" and "Capture Main Screen" are checked, and "ET05R" is selected as the secondary source, indicated by a red arrow. The "Add Another Video Source" button is at the bottom left. The main recording area shows a dark screen with "Secondary Source" text and a red arrow pointing to the "ET05R" tab in the browser window above. At the bottom, the "Resolution" is "1920 x 1080" and the "fps" is set to "24", both highlighted with red boxes.

Zoom Settings for BKENG Grand Hall

Test Speaker and Microphone every time!

Best Camera: USB Capture HDMI

Best Microphone: HDMI (2-USB Capture HDMI)

Document Camera: Share Screen, choose Advanced and select Content from Second Camera (toggle Switch Camera button)

Laptop Capture: Set Room control to Laptop. Connect to ShareLink. Run Zoom session from the laptop



A screenshot of the Zoom settings interface. On the left, the 'Speaker' section shows 'Test Speaker' and 'SVSi N2400 (Intel(R) Display Audi...' selected, with an 'Output Level' slider and a 'Volume' slider. Below it, the 'Microphone' section shows 'Test Mic' and 'HDMI (2- USB Capture HDMI)' selected. A 'Select a Microphone' dropdown menu is open, listing 'HDMI (2- USB Capture HDMI)' (checked), 'Microphone Array (Synaptics Audio)', 'HDMI (USB Capture HDMI)', and 'Same as System'. Below that, a 'Select a Speaker' dropdown menu is open, listing 'Speakers (Synaptics Audio)', 'SVSi N2400 (Intel(R) Display Audio)' (checked), and 'Same as System'. On the right, the 'Camera' section shows 'USB Capture HDMI' selected. Below it, '16:9 (Widescreen)' is selected with a radio button, and 'Original Ratio' is unselected. Under 'My Video', 'Mirror my video' is checked, while 'Enable HD', 'Touch up my appearance', and 'Adjust for low light' are unselected. At the bottom right, a 'Select a Camera (Alt+N to switch)' dropdown menu is open, listing 'ET05R', 'USB Capture HDMI' (checked), 'USB Capture HDMI', and 'Integrated Camera'. Below that are 'Choose Virtual Background' and 'Video Settings...'. At the very bottom, the Zoom control bar shows 'Stop Video', 'Security', and 'Participants' (1).